

**Warranty:**

The frame and Mackie hinge of your brace are covered by a one year limited warranty against defects in materials or craftsmanship soft goods are covered by a six month limited warranty.

**Ortho Innovations' Custom Fabricated Products Order Form**

Date \_\_\_\_\_ Date Needed \_\_\_\_\_ P.O. # \_\_\_\_\_

**BILLING INFORMATION**

Facility \_\_\_\_\_ Contact Name \_\_\_\_\_  
 Billing Address \_\_\_\_\_  
 City \_\_\_\_\_ State \_\_\_\_\_ Zip \_\_\_\_\_  
 Phone \_\_\_\_\_ Fax \_\_\_\_\_

**SHIPPING INFORMATION**

Facility \_\_\_\_\_ Shipping Address \_\_\_\_\_  
 City \_\_\_\_\_ State \_\_\_\_\_ Zip \_\_\_\_\_  
 Phone \_\_\_\_\_ Fax \_\_\_\_\_

**SHIP VIA FEDEX**

Ground (FXGD)     Standard 2 Day (FX2D)     Priority (FX1D)     1st Overnight (FX1A)     Other

**PATIENT INFORMATION**

Patient ID \_\_\_\_\_ Height \_\_\_\_\_ Weight \_\_\_\_\_ Age \_\_\_\_\_  
 Physician \_\_\_\_\_ Diagnosis \_\_\_\_\_  
 Special Instructions: \_\_\_\_\_

**Important Note:** If a patient presents with excessive varus or valgus angulation at the joint or if you are concerned about another irregularity in the patient's limb shape when ordering a custom brace, the device can be built to a tracing or a cast of the patient's limb. Tracings should be taken with the tracing board in the frontal plane and by creasing the board at the joint center.

**Custom Fabricated Elbow Extension Brace – with removable knob**

*How to measure for a Pre-fabricated Elbow Brace:*

1. Facing the patient, position the elbow in maximum extension and the wrist in neutral pronation/supination. See diagram to check proper positioning for measurement.
2. A circumference measurement should be taken around the arm at each level.
3. A diameter, medial to lateral (M-L) measurements, is also needed at each level.

**Level A** - is located 7 inches above joint center.

**Level B** - is located at the joint center. M-L should be taken in line with the humeral condyles and reflect the widest M-L.


**Level C** - is located 7 inches below joint center.

**Patient's Measurements for Custom Elbow Brace**

Affected Elbow: **LEFT** or **RIGHT**  
 Knob Placement: **MEDIAL** or **LATERAL**

Standard Overall Length = 14 inches (specify if other): \_\_\_\_\_

Humeral Section: \_\_\_\_\_ Forearm Section: \_\_\_\_\_  
 (7" Standard) " (7" Standard) "



	Circumference	M-L
LEVEL A	Ⓐ " Ⓐ "	
LEVEL B	Ⓑ " Ⓑ "	
LEVEL C	Ⓒ " Ⓒ "	

**Custom Fabricated Knee Extension Brace – with removable knob**

*How to measure for a Custom Knee Brace:*

1. Patient may be seated or lying down for measurements. Position leg in maximum extension.
2. A circumference measurement is the distance around the leg and should be taken at each level.
3. A diameter, medial to lateral (M-L) measurements, is the width of the leg and is needed at each level.

**Level A** - is located 10 inches above joint center.

**Level B** - is located at the joint center. M-L should be taken in line with mid patella and reflect the widest M-L.


**Level C** - is located 10 inches below joint center.

**Patient's Measurements for Custom Knee Brace**

Affected Knee: **LEFT** or **RIGHT**

Standard Overall Length = 20 inches (specify if other): \_\_\_\_\_

Thigh Section: \_\_\_\_\_ Calf Section: \_\_\_\_\_  
 (10" Standard) " (10" Standard) "



	Circumference	M-L
LEVEL A	Ⓐ " Ⓐ "	
LEVEL B	Ⓑ " Ⓑ "	
LEVEL C	Ⓒ " Ⓒ "	